

## Help Sheet - TPN Price Override within Loadmaster

You can charge customers in a variety of ways but to retain a TPN style of charging use the TPN Pricing Override. This is found on Setup/Networks/TPN/TPN Pricing/ TPN Global Pricing Override.

Choose the Service then fill the screen out as required.

Create/Amend TPN Price Override

TPN Service Code  \* Leave BLANK if using spawning

From Zone  To Zone

Use Quarter Pallets  Use Half Pallets  Use Full Pallets

Quarter Charge \*  Half Charge \*  Full Charge \*

Charge per pallet  Charge per pallet  Charge per pallet

Upto items  Upto items  Upto items

Then charge  Then charge  Then charge

Override Quarter upto  Override Half upto  Override Full upto

Use Half Oversize Pallets  Use Full Oversize Pallets

H/O/S Charge \*  O/S Charge \*

Charge per pallet  Charge per pallet

Upto items  Upto items

Then charge  Then charge

Override H/O/S upto  Override F/O/S upto

The charges marked \* are normally set to zero unless you wish to add this to the total consignment

To replicate the charges from one zone to another then pick an existing rate and put a value in this 'To' Zone box then hit CLONE To Zone  Clone

To replicate the charges from one service to another then pick an existing rate and put a value in this 'Service' box then hit CLONE Service  Clone

SPAWNING mass replicates an existing rate to another set of services in the same zone. This bulk updates a series of services that you select. It will open a new window to select these. Spawn

SAVE Cancel

You tick the Use box to apply the different types of freight. The boxes marked with a \* are added to the computed charges and in general should be zero.

Looking at this example -

1 quarter pallet will be charged at £35.00 and each one thereafter will be charged at £35.00.

To charge extra pallets at £34.00 you would place 34 on the 'Then charge' field.

To charge the first 2 pallets at £35.00 and the subsequent at £34.00 you place a 2 on the 'Upto items' field and then 34 on the 'Then charge field'.

The Override Quarter pallet field is used where you want to charge the 'Then charge' value on all the pallets when it goes beyond the 'Upto items' instead of just adding the new totals to the running totals. Note the CLONE buttons which allow copying to other regions and services.

The options at the bottom allow replication of the current rate.

1. You can copy the current rate to a different zone.
2. You can copy the current rate to a different service.
3. You can mass replicate to another set of services for the existing zone.

Note: The last option will open up a further box where you can select as many other services to copy to as you want.

