

## TPN Lite (Customer Implant) Settings

### Default Login to View the Usertable

**Username:** manager

**Password:** borg

---

If FTP or PCA address doesn't work, use the following IP numbers below:

**FTP IP** - 62.172.111.35 (<ftp.tpnmail.co.uk>)

**PCA IP** - 91.209.178.241 ([www.tpn1.tzo.com](http://www.tpn1.tzo.com))

---

### Label Settings

**Name** TPN Label

**Label Size Width** 101.6

**Label Size Height** 203.2

**Orientation** Portrait

Use the **Seagull** driver for the **Zebra LP2844**.



Use the same **seagull** driver for the printers - **Zebra LP 2844Z** and **Zebra GK 420D**, but instead of **Portrait**, select **Portrait 180°**.

**NOTE:** If the label does not print correctly, click on the ‘**Advanced**’ tab’ on the printer properties and click **Printing Defaults**. The settings on the printing defaults should be the same as the settings in printing preferences. If they are not the same, change them to the correct settings.

